

Robot CLI Command Tools

Robot CLI Command Tools

1. Course Content
 - Course Overview
 - Learning Objectives
2. Preparation
3. Introduction to CLI Tools
4. CLI Command Robot Control Communication Architecture
5. Controlling the Robot with CLI
 - 5.1 CLI Command Summary
 - 5.2 Tools Supported by Different Vehicle Versions
 - 5.3 Command Format
6. Demo Cases
7. Source Code Analysis

1. Course Content

Course Overview

- This lesson explains the use of the robot CLI (Command Line Interface) command tools. Through the command line interface, users can directly control various functions of the robot, such as chassis movement and visual recognition.
- The CLI command tools encapsulate all MCP Tool interfaces. Without relying on an AI model, you can quickly control the robot, which is convenient for functional testing and debugging.

Learning Objectives


1. Understand the functional positioning and application scenarios of the robot CLI command tools
2. Become familiar with the functions, parameters, and usage format of CLI commands

[!IMPORTANT]

The demo in this lesson uses the pan-tilt camera version (PTZ) as an example; the MCP and CLI tool types may differ slightly across different vehicle versions

2. Preparation

```
ros2 launch microros_v2_bringup openclaw_service.launch.py
```

5. Controlling the Robot with CLI

5.1 CLI Command Summary

You can view the list of all available CLI commands with `robot_control list-tools`. The following is a summary of all currently registered CLI commands:

Command	Parameters	Function
Move	--direction, --distance, -angle	Move the robot chassis by a specified distance or rotate by a specified angle. <code>direction</code> options: <code>forward</code> , <code>backward</code> , <code>turn_left</code> , <code>turn_right</code>
Seewhat	None	Capture one frame of image and return the saved path
AdjustCameraView	--pitch, --yaw	Adjust the camera view. <code>pitch</code> controls tilt (positive = up, negative = down), <code>yaw</code> controls pan (positive = right, negative = left); a step of 5-10 degrees is recommended
GetBbox	--query	Detect and return the bounding box (bbox) coordinates of the target object based on a text description
TargetTrack	--x1-or-cmd, -y1, --x2, --y2	Visual tracking of the target object. Pass <code>cancel</code> to stop tracking
FollowLine	--color	Follow a colored route on the ground. <code>color</code> options: <code>red</code> , <code>green</code> , <code>blue</code> , <code>yellow</code>
CameraActionGroup	--action_name	Execute camera preset action groups. Options: <code>init_camera_pose</code> , <code>nod</code> , <code>shake</code>
Navigation	--location	Navigate to a target location; the parameter is the location symbol in the map mapping file
RecordMapLocation	--name, --symbol	Save the current location to the map mapping file
GetMapMapping	None	Get the mapping relationship between all location names and their corresponding symbols

5.2 Tools Supported by Different Vehicle Versions

- Basic version - basic_car (no vision functions): Move, Navigation, RecordMapLocation, GetMapMapping
- Standard version - no_ptz (no pan-tilt functions): Move, Navigation, RecordMapLocation, GetMapMapping, SeeWhat, GetBbox, TargetTrack, FollowLine
- Servo pan-tilt version - ptz (supports all functions)

[NOTE]

The demo cases in the following chapters use the servo pan-tilt version (ptz) vehicle

5.3 Command Format

All CLI commands follow a unified command format:

```
robot_control call-tool <command-name> --parameter1 <value1> --parameter2
<value2> ...
```

- `robot_control`: The main command of the CLI tool
- `call-tool`: The subcommand indicating a tool call
- `<command-name>`: The specific tool name registered on the MCP server, such as `Move`, `Seewhat`, `TTS`, etc.
- `--parameter <value>`: The key-value pair of parameters passed as needed; different commands have different numbers and types of parameters

Use `robot_control list-tools` to view the list of all available CLI commands

6. Demo Cases

- The robot chassis moves forward 0.5 meters

```
robot_control call-tool Move --distance 0.5 --direction forward
```

```
yahboom@yahboom:~$ robot_control call-tool Move --distance 0.5 --direction forward
{
  "execution_result": "success",
  "reason": "Moved forward 0.480m"
}
```


- Get an image of the environment (only for versions with a camera)

```
robot_control call-tool Seewhat
```

```
yahboom@yahboom:~$ robot_control call-tool SeeWhat
{
  "result": {
    "image": "/home/yahboom/microros_ws/cache/image.png"
  }
}
```

[!NOTE]

When the SeeWhat tool is called, it automatically saves the image to
`"$HOME/microros_ws/cache/image.png"`



7. Source Code Analysis

Source Code Path:

```
$HOME/microros_ws/src/multi_brains_pre/cli/robot_control
```

The CLI tool source code registers the various robot control functions as MCP Tools through the `register_actions()` function in `mcp_action.py`. Here, the `Move` (move the chassis by a specified distance) tool is used as an example to explain the source code:

```
@call_tool_app.command(name='Move')
async def Move(
    *,
    direction: Annotated[str, cyclopts.Parameter(help="Movement direction:
'forward', 'backward', 'turn_left', or 'turn_right'")],
    distance: Annotated[float, cyclopts.Parameter(help="Linear movement distance
in meters. Only used when direction is 'forward' or 'backward'. Set to 0.0 for
rotation.")],
    angle: Annotated[float, cyclopts.Parameter(help="Rotation angle in degrees.
Only used when direction is 'turn_left' or 'turn_right'. Set to 0.0 for linear
movement.")],
) -> None:
    '''Move the robot chassis by a specified distance or rotate by a specified
angle using odometry feedback.'''
    await _call_tool('Move', {'direction': direction, 'distance': distance,
'angle': angle})
```

Code explanation:

1. **@call_tool_app.command(name='Move')**: Uses the `cyclopts` framework to register the function as a CLI subcommand; `name` defines the command name, corresponding to the tool name registered on the MCP server
2. **Function parameters**: CLI parameters are defined through the `Annotated` type annotation plus `cyclopts.Parameter`; `help` sets the parameter description. `direction` is a required parameter, while `distance` and `angle` are optional parameters with a default value of 0.0
3. **_call_tool**: A unified tool call function. Internally, it connects to the MCP server through `fastmcp.Client`, filters the parameters, sends them to the server for execution, and prints the returned result